

Computer Networks

Exercise Session 03

Prof. Dr. Oliver Hahm

Frankfurt University of Applied Sciences
Faculty 2: Computer Science and Engineering
oliver.hahm@fb2.fra-uas.de
<https://teaching.dahahm.de>

November 11, 2022

General Schedule

All exercises will follow this general schedule

- Identify potential understanding problems
 - Ask your questions
 - Recap of the lecture
- Address the understanding problems
 - Answer your questions
 - Repeat certain topics
- Walk through the exercises/solutions → Some hints and guidance
 - Work time or presentation of results

Fundamentals of Data Signals

You have seen ...

- how an **analog** signal can be transformed into a **digital** signal (and vice versa) using **quantization** and **sampling**
- how often a channel needs to be sampled to reconstruct the original analog signal
- how a **square wave signal** can be constructed by a **fundamental frequency** and its **harmonics**
- the difference between **bandwidth**, **data rate**, and **symbol rate**
- what data rate can be achieved on a **noiseless** and a **noisy channel** with **finite bandwidth**

Data Encoding

You have seen ...

- what a **baseband** transmission is
- which **requirements** exist for a good encoding (**robustness**, **efficiency**, and **clock recovery**)
- several **line codes** and how they relate to these requirements
- what the problems of **baseline wander** and **clock recovery** are and how to tackle them
- how an encoding of **group of bits** in combination of another encoding can be used to address all requirements → e.g., **4B/5B**

Modulation

You have seen ...

- how data can be **modulated** onto a **carrier frequency** in **broadband**
- what **amplitude**, **frequency**, and **phase modulation** are
- which advantages and drawbacks these methods have

Transmission Media

You have seen ...

- which **categories** of transmission media exist
- common types of **guided** transmission media (**coaxial**, **twisted pair**, and **fiber optic**)
- what the common challenges of **wireless** networks are
- how the **last mile** can be bridged in a cost-efficient manner

Technologies

You have seen ...

- how **Ethernet** has evolved to become the most popular wired LAN technology
- what **Token Ring** was and why it became obsolete
- which types of **WLAN** exist and how they differ
- what **Bluetooth**, piconets, scatternets, and **BLE** are


Any other questions left?




Exercise 1: Layers of Reference Models

- Protocol example for the **session layer**
 - **Point-to-Point Tunneling Protocol (PPTP)** was used for **Virtual Private Networks (VPNs)**
 - Encapsulate layer 2 frames into a **TCP** control channel
 - Layer 3 protocols like **IP** can be transported over PPTP
 - **Password Authentication Protocol (PAP)** can be used for password-based authentication
- Protocol example for the **presentation layer**
 - **External Data Representation (XDR)** is a data **serialization** format
 - It allows for **de-** and **encoding** between different representations of data types
 - Supported data types comprise: boolean, int, float, enumerations ...
 - An example can be found here:
<https://github.com/brendanhay/xdr/blob/master/example.xdr>


Exercise 2: Quantization and Sampling



Exercise 2: Quantization and Sampling



Exercise 2: Quantization and Sampling



- Until the 1980s the whole telephone system was **voice only**
⇒ the lowest frequency was **300 Hz**, the highest frequency was **3.4 kHz**

Exercise 3 and 4: Bit, Symbol and Data Rate

Remember the differences between bit rate and symbol rate:

Bit rate

- The number of bits that can be transmitted per unit of time
- Typically expressed as **bit/s**, or **bps** in conjunction with a **SI** prefix
- The physical layer defines the **gross bitrate**
- It is also used in digital **multimedia** to represent the number of bits used to encode audio or videos


Baud rate

- Number of symbol or waveform changes per unit of time
- Typically expressed as **baud (Bd)**
- The **symbol duration time** or **unit interval** is T_s
$$T_s = \frac{1}{f_s}$$
where f_s is the symbol rate

The **bit rate** depends on the **bandwidth** of the communication channel and the **number of bits per symbol**

Exercise 5 and 6: Manchester II Encoding


- This line code (also called **Biphase-L** is the opposite of the Manchester encoding
 - Manchester encoding:
 - Transition from high to low signal corresponds to a logical 0 bit
 - Transition from low to high signal corresponds to a logical 1 bit
 - Manchester II encoding:
 - Transition from low to high signal corresponds to a logical 0 bit
 - Transition from high to low signal corresponds to a logical 1 bit
- Just as for the Manchester encoding, **clock recovery is possible** for the receiver and **baseline wander cannot occur** because the usage of the signal levels is distributed equally



Manchester II Code


A	B	A XOR B
0	0	0
0	1	1
1	0	1
1	1	0

- The Manchester II encoding is calculated via **exclusive or (XOR)** of the NRZ encoded data and the clock



Alternate Mark Inversion (AMI code) = Bipolar Encoding

- Uses 3 signal levels (+, 0 und -)
 - Logical 0 bits are encoded as middle signal level (0)
 - Logical 1 bits are alternating encoded as high (+) or low signal level (-)
- Benefit: Baseline wander cannot occur
- Drawback: Clock recovery is impossible for series of logical 0 bits
- Error detection is partly possible because the signal sequences ++, --, +0+ and -0- are illegal



AMI Line Code in Practice and Scramblers

The ISDN S_0 bus uses a modified version of the AMI line code


- With this variant, logical 1 bits are encoded as middle signal level and logical 0 bits are alternating encoded as high signal level or low signal level
 - To allow for clock recovery a **scrambler** is often used, after AMI line code encoding
- ⇒ A scrambler is a device, which modifies a bit stream according to a simple algorithm in a way, that it is simple to reverse back to the original bit stream
- In this case, scramblers are used, to interrupt long series of logic 0 bits

Encoding Data

Image source: Wikipedia (CC0)

- Efficient data encoding is important not only since the rise of computer networks
- An example for an efficient encoding is the **Morse Code**, invented by Samuel Morse from 1838

A	· —	M	— —	Y	— · — —
B	— · · ·	N	— ·	Z	— — · ·
C	— · — ·	O	— — —	1	· — — — —
D	— · ·	P	· — — ·	2	· · — — —
E	·	Q	— — · —	3	· · · — —
F	· · — ·	R	· — ·	4	· · · · —
G	— — ·	S	· · ·	5	· · · · ·
H	· · · ·	T	—	6	— · · · ·
I	· ·	U	· · —	7	— — · · ·
J	· — — —	V	· · · —	8	— — — · ·
K	— · —	W	· — —	9	— — — — ·
L	· — · ·	X	— · · —	0	— — — — —



Samuel Morse (1791 – 1872)